

rancher 패스워드 초기화 방법

rancher를 설치하고 나서 root사용자 패스워드 초기화가 필요한 경우 수행하면 됩니다.

작업방법

1. rancher pod 정보 확인

```
$> kubectl get pod -A | grep rancher
cattle-system          rancher-c56764479-nt7nb          1/1   Running   3 (3d2h ago)   45d
```

2. rancher pod가 어느노드에서 났는지 확인

```
$> kubectl describe pod rancher-c56764479-nt7nb -n cattle-system
Name:          rancher-c56764479-nt7nb
Namespace:     cattle-system
Priority:       1000000000
Priority Class Name: rancher-critical
Node:          test2/192.168.0.25
Start Time:    Thu, 21 Sep 2023 00:51:03 +0900
Labels:        app=rancher
               pod-template-hash=c56764479
               release=rancher
Annotations:   cni.projectcalico.org/containerID: f44aa8d23b68a7376bc29e0bc66605670dc5a87daa9c668bd4f241aa4b63b492
               cni.projectcalico.org/podIP: 10.233.64.107/32
               cni.projectcalico.org/podIPs: 10.233.64.107/32
Status:        Running
IP:            10.233.64.107
IPs:
  IP:          10.233.64.107
Controlled By: ReplicaSet/rancher-c56764479
```

3. rancher 컨테이너 정보 확인 (test2노드에서 실행)

```
$> crictl ps | grep rancher
a68dc79ee1d8c    81ee0878ffcdc    26 minutes ago    Running          rancher          3          f44aa8d23b68a    rancher-c56764479-nt7nb
```

4. rancher 컨테이너로 패스워드 초기화 (test2노드에서 실행)

```
$> crictl exec a68dc79ee1d8c reset-password
W1104 17:53:31.241158    386 client_config.go:617] Neither --kubeconfig nor --master was specified. Using the inClusterConfig. This might not work.
New password for default admin user (user-q2kl4):
123123
```

reference

- <https://nevido.tistory.com/740>
-

★Created 5 November 2023 02:54:01 by artop0420

✎Updated 14 April 2024 00:18:48 by artop0420